

Example Calculations of CP-VASP

Table of contents

Fixed structure calculation	2
Ionic Relaxation	4
Molecular Dynamics, Exact Potential.....	7
Molecular Dynamics, Grand-Canonical.....	11

All the following examples are for a 3x3x1 super cell of Pt(111), expect for the grand-canonical MD case which uses a unit cell of Pt(100). We have supplied the INCAR, POSCAR, and KPOINTS files.

Fixed Structure:

INCAR:

General VASP parameters

*ISTART = 0
ENCUT = 400
ISPIN = 1
ISMEAR = 1
SIGMA = 0.2
ALGO = Normal
ISYM = 0
LREAL = Auto
LWAVE = .FALSE.
LCHARG = .FALSE.*

*NSW = 0
NELM = 120
POTIM = 0.5
IBRION = -1
EDIFF = 1E-6*

VASPsol++ Solvent Model - This corresponds to water

*LSOL = .TRUE.
ISOL = 2
C_MOLAR = 1.0
R_ION = 4.0*

CP-VASP Parameters

*LCEP = .TRUE.
NESCHEME = 1
CAP_MAX = 2.0
TARGETMU = -4.57
FERMICONVERGE = 0.01*

#####

POSCAR:

slab-pt111

1.0

<i>8.4899997711</i>	<i>0.0000000000</i>	<i>0.0000000000</i>
<i>4.2449998856</i>	<i>7.3525554799</i>	<i>0.0000000000</i>

	0.0000000000	0.0000000000	25.0000000000
<i>Pt</i>			
27			
<i>Direct</i>			
0.000000000	0.000000000	0.080872335	
0.000000000	0.333333343	0.080872335	
0.000000000	0.666666687	0.080872335	
0.333333343	0.000000000	0.080872335	
0.333333313	0.333333343	0.080872335	
0.333333313	0.666666687	0.080872335	
0.666666687	0.000000000	0.080872335	
0.666666687	0.333333343	0.080872335	
0.666666627	0.666666687	0.080872335	
0.111111112	0.111111112	0.172000006	
0.111111112	0.444444448	0.172000006	
0.111111119	0.777777791	0.172000006	
0.444444448	0.111111112	0.172000006	
0.444444448	0.444444448	0.172000006	
0.444444448	0.777777791	0.172000006	
0.777777791	0.111111112	0.172000006	
0.777777791	0.444444448	0.172000006	
0.777777791	0.777777791	0.172000006	
0.222222224	0.222222224	0.263127685	
0.222222224	0.555555582	0.263127685	
0.222222224	0.888888896	0.263127685	
0.555555582	0.222222224	0.263127685	
0.555555562	0.555555582	0.263127685	
0.555555522	0.888888896	0.263127685	
0.888888896	0.222222224	0.263127685	
0.888888896	0.555555582	0.263127685	
0.888888896	0.888888896	0.263127685	



KPOINTS:

K-Points
0
M
7 7 1

Analysis:

These plots depict the change in the number of electrons and the electrolyte-referenced Fermi level ($E_F - e\Phi$), which is related to the interfacial potential by Eq.

1 in the manual. The last printout occurs at the end of an ionic step when the target potential is reached.



Ionic Relaxation:

INCAR:

General VASP parameters

ISTART = 0

ENCUT = 400

ISPIN = 1

ISMear = 1
SIGMA = 0.2
ALGO = Normal
ISYM = 0
LREAL = Auto
LWAVE = .FALSE.
LCHARG = .FALSE.

NSW = 200
NELM = 120
IBRION = 2
EDIFFG = -0.01
EDIFF = 1E-6

VASPsol++ Solvent Model - This corresponds to water

LSOL = .TRUE.
ISOL = 2
C_MOLAR = 1.0
R_ION = 4.0

CP-VASP Parameters

LCEP = .TRUE.
NEScheme = 2
CAP_MAX = 2.0
TARGETMU = -4.57
FERMICONVERGE = 0.01

#####

POSCAR:

slab-pt111

1.0

<i>8.4899997711</i>	<i>0.0000000000</i>	<i>0.0000000000</i>
<i>4.2449998856</i>	<i>7.3525554799</i>	<i>0.0000000000</i>
<i>0.0000000000</i>	<i>0.0000000000</i>	<i>25.0000000000</i>

Pt

27

Direct

<i>0.006663528</i>	<i>0.997492492</i>	<i>0.082663290</i>
<i>0.000521697</i>	<i>0.336543232</i>	<i>0.080099314</i>
<i>0.005466287</i>	<i>0.664497674</i>	<i>0.079137705</i>
<i>0.333856165</i>	<i>0.998869538</i>	<i>0.077634916</i>
<i>0.334888101</i>	<i>0.324505597</i>	<i>0.079542175</i>
<i>0.334581316</i>	<i>0.658504605</i>	<i>0.086563498</i>
<i>0.667036951</i>	<i>0.005466488</i>	<i>0.073986299</i>

0.669289172	0.338651121	0.087669782
0.667903304	0.662064791	0.079864971
0.119142771	0.107272796	0.169080883
0.110557854	0.452726841	0.168670118
0.102894939	0.774473071	0.173215792
0.445798576	0.116315737	0.169163182
0.442165822	0.439048529	0.174396932
0.437628865	0.770166159	0.168667227
0.774587274	0.105807371	0.174271643
0.783584952	0.436009407	0.173507273
0.785915554	0.771487415	0.172938839
0.222130090	0.225648865	0.257908911
0.213626161	0.562005401	0.268385768
0.220870987	0.888177812	0.261690706
0.557420194	0.219741940	0.256159335
0.555504680	0.563429475	0.260394722
0.550366044	0.886049271	0.265101939
0.878893554	0.214194626	0.264638543
0.887896359	0.557410359	0.270572752
0.888455927	0.885109484	0.262081265

KPOINTS:

K-Points



0

M

7 7 1

Analysis:

These plots depict the change in the number of electrons and the electrolyte-referenced Fermi level with the number ionic steps. The single-SCF algorithm allows the structure to evolve before converging the interfacial potential, which leads to an overestimation in the electron number at the third step. The algorithm quickly corrects this and reaches the target potential. As we are only interested in the final structure for ionic relaxation calculations, we can conclude the relaxation was successful.



Molecular Dynamics, Exact Potential:

INCAR:

General VASP parameters

ISTART = 0

ENCUT = 400

ISPIN = 1

ISMear = 1

SIGMA = 0.2

ALGO = Normal

```

ISYM = 0
LREAL = Auto
LWAVE = .FALSE.
LCHARG = .FALSE.

```

```

NSW = 200
NELM = 120
POTIM = 1.0
IBRION = 0
EDIFF = 1E-6

```

```

# MD Parameters

```

```

MDALGO = 2
SMASS = 0
TEBEG = 300 ; TEEND = 300

```

```

# VASPsol++ Solvent Model - This corresponds to water

```

```

LSOL = .TRUE.
ISOL = 2
C_MOLAR = 1.0
R_ION = 4.0

```

```

# CP-VASP Parameters

```

```

LCEP = .TRUE.
NESHEME = 2
CAP_MAX = 2.0
NEADJUST = 5
TARGETMU = -4.57
FERMICONVERGE = 0.01

```

```

#####

```

POSCAR:

slab-pt111

1.0

8.4899997711	0.0000000000	0.0000000000
4.2449998856	7.3525554799	0.0000000000
0.0000000000	0.0000000000	25.0000000000

Pt

27

Direct

0.001762321	0.998047650	0.080491915
0.001887487	0.331347734	0.080466107
0.001813437	0.664667308	0.080472529
0.335080028	0.998123407	0.080473177

0.335131705	0.331413895	0.080480568
0.335153550	0.664781034	0.080469668
0.668451726	0.998044491	0.080477387
0.668481946	0.331455767	0.080472335
0.668559313	0.664692283	0.080480225
0.110985793	0.109551027	0.171785563
0.111008994	0.442953557	0.171790078
0.110996664	0.776247025	0.171779588
0.444282383	0.109575853	0.171783373
0.444260418	0.442963362	0.171769798
0.444367290	0.776289523	0.171737522
0.777635515	0.109633319	0.171790898
0.777793884	0.442909002	0.171796143
0.777669430	0.776287138	0.171781719
0.220234841	0.221408457	0.263072968
0.220300481	0.554729819	0.263103038
0.220258161	0.888045967	0.263084829
0.553577840	0.221359968	0.263051420
0.553608060	0.554722667	0.275039881
0.553578556	0.888020337	0.263091862
0.886944354	0.221427798	0.263090938
0.886895120	0.554858267	0.263104260
0.886927843	0.888113618	0.263070077

KPOINTS:

K-Points



0


M

7 7 1

Analysis:

These plots depict the change in the number of electrons, the electrolyte-referenced Fermi level, and the grand canonical energy (GCE) with the number of ionic steps. Because we set NEADJUST = 5, the electron number is only adjusted every 5 steps. Consequently, the electronic information is only printed every 5 steps. The initial jump in the GCE is due to the potentiostat reaching convergence with the single-SCF algorithm. The steady increase in the GCE overtime is due to the sluggish dynamics of the Pt system, as Pt has a high mass and the interatomic vibrations have large periods. The GCE would begin to drop if the simulation were continued over additional ionic steps. Performing MD without the constant-potential condition will yield a similar behavior.





Molecular Dynamics, Grand-Canonical:

INCAR:

General VASP parameters

```

ISTART = 0
ENCUT = 400
ISPIN = 1
ISMear = 1
SIGMA = 0.2
ALGO = Fast
ISYM = 0
LREAL = .FALSE.
LWAVE = .FALSE.
LCHARG = .FALSE.

```

```

NSW = 200
NELM = 120
POTIM = 1.0
IBRION = 0
EDIFF = 1E-6

```

MD Parameters

```

MDALGO = 2
SMASS = 0
TEBEG = 300 ; TEEND = 300

```

VASPsol++ Solvent Model - This corresponds to water

LSOL = .TRUE.

ISOL = 2

C_MOLAR = 1.0

R_ION = 4.0

CP-VASP Parameters

LCEP = .TRUE.

NESHEME = 5

NEADJUST = 1

TARGETMU = -4.57

T_eta = 300

eta_length = 1

#####

POSCAR:

slab-pt100

1.0

2.7882300000 0.0000000000 0.0000000000

0.0000000000 2.7882300000 0.0000000000

0.0000000000 0.0000000000 35.0000000000

Pt

3

Cartesian

0.0000000000 0.0000000000 1.0000000000

1.394115000 1.394115000 2.971575000

0.0000000000 0.0000000000 4.943150000

KPOINTS:

K-Points

0

M

13 13 1

Analysis:

These plots depict the change in the number of electrons and the electrolyte-referenced Fermi level with the number of ionic steps. Unlike the previous examples where the Fermi level is aggressively tuned to the target potential, the electron number is allowed to fluctuate so that the grand-canonical ensemble is correctly

sampled. The behavior of these fluctuations is highly sensitive to the input parameters and may require tuning when simulating new systems.

